

**Security Group: CATALOGADMIN - Catalog Admin group, has all catalog permissions.**

CATALOG_ADMIN	ALL operations in the Catalog Manager.
---------------	--

**Security Group: CATALOGADMIN\_LTD - Limited Catalog Admin group, has limited catalog permissions.**

CATALOG_ROLE_CREATE	Limited Create operations in the Catalog Manager.
CATALOG_ROLE_DELETE	Limited Delete operations in the Catalog Manager.
CATALOG_ROLE_UPDATE	Limited Update operations in the Catalog Manager.
CATALOG_VIEW	View operations in the Catalog Manager.

**Security Group: FLEXADMIN - Flexible Admin group, has all granular permissions.**

ACCOUNTING_CREATE	Create operations in the Accounting Manager.
ACCOUNTING_DELETE	Delete operations in the Accounting Manager.
ACCOUNTING_UPDATE	Update operations in the Accounting Manager.
ACCOUNTING_VIEW	View operations in the Accounting Manager.
CATALOG_CREATE	Create operations in the Catalog Manager.
CATALOG_DELETE	Delete operations in the Catalog Manager.
CATALOG_PRICE_MAINT	Permission required, in addition to other applicable permissions, to maintain product price information including prices, promotions, and price rules.
CATALOG_UPDATE	Update operations in the Catalog Manager.
CATALOG_VIEW	View operations in the Catalog Manager.
CONTENTMGR_CREATE	Create operations in the Content Manager.
CONTENTMGR_DELETE	Delete operations in the Content Manager.
CONTENTMGR_UPDATE	Update operations in the Content Manager.
CONTENTMGR_VIEW	View operations in the Content Manager.
DATAFILE_MAINT	Use the Data File Maintenance pages.
ENTITY_DATA_CREATE	Create with the Entity Data Maintenance pages.
ENTITY_DATA_DELETE	Delete with the Entity Data Maintenance pages.
ENTITY_DATA_UPDATE	Update with the Entity Data Maintenance pages.
ENTITY_DATA_VIEW	View with the Entity Data Maintenance pages.
ENTITY_MAINT	Use the Entity Maintenance pages.
ENTITY_SYNC_ADMIN	Use the Entity Sync Admin pages.
ENUM_STATUS_MAINT	Use the Enum and Status Maintenance pages.
FACILITY_CREATE	Create operations in the Facility Manager.
FACILITY_DELETE	Delete operations in the Facility Manager.
FACILITY_UPDATE	Update operations in the Facility Manager.
FACILITY_VIEW	View operations in the Facility Manager.
MANUAL_PAYMENT	Manual Payment Transaction.
MANUFACTURING_CREATE	Create operations in the Manufacturing Manager.
MANUFACTURING_DELETE	Delete operations in the Manufacturing Manager.
MANUFACTURING_UPDATE	Update operations in the Manufacturing Manager.
MANUFACTURING_VIEW	View operations in the Manufacturing Manager.
MARKETING_CREATE	Create operations in the Marketing Manager.
MARKETING_DELETE	Delete operations in the Marketing Manager.
MARKETING_UPDATE	Update operations in the Marketing Manager.
MARKETING_VIEW	View operations in the Marketing Manager.
ORDERMGR_CREATE	Create operations in the Order Manager.
ORDERMGR_DELETE	Delete operations in the Order Manager.
ORDERMGR_NOTE	Create notes in the Order Manager.
ORDERMGR_RETURN	Process returns in the Order Manager.
ORDERMGR_UPDATE	Update operations in the Order Manager.
ORDERMGR_VIEW	View operations in the Order Manager.
PARTYMGR_CREATE	Create operations in the Party Manager.
PARTYMGR_DELETE	Delete operations in the Party Manager.
PARTYMGR_NOTE	Create notes in the Party Manager.
PARTYMGR_UPDATE	Update operations in the Party Manager.
PARTYMGR_VIEW	View operations in the Party Manager.

PAYPROC_CREATE	Create operations in the Payment Processors Setup.
PAYPROC_DELETE	Delete operations in the Payment Processors Setup.
PAYPROC_VIEW	View operations in the Payment Processors Setup.
PAY_INFO_CREATE	Create Payment Information.
PAY_INFO_DELETE	Delete Payment Information.
PAY_INFO_UPDATE	Update Payment Information.
PAY_INFO_VIEW	View Payment Information.
PERIOD_MAINT	Use the Period Maintenance pages.
RULES_MAINT	Use the Rules Maintenance pages.
SECURITY_CREATE	Create operations in the Security Management Screens.
SECURITY_DELETE	Delete operations in the Security Management Screens.
SECURITY_UPDATE	Update operations in the Security Management Screens.
SECURITY_VIEW	View operations in the Security Management Screens.
SEND_CONTROL_APPLET	Send to the Control Applet.
SERVER_STATS_VIEW	View the Server Statistics pages.
SERVICE_INVOKE_ANY	Permission to invoke any service remotely.
SERVICE_MAINT	Use the Service Maintenance pages.
SHIPRATE_CREATE	Create operations in the Shipping Rate Editor.
SHIPRATE_DELETE	Delete operations in the Shipping Rate Editor.
SHIPRATE_VIEW	View operations in the Shipping Rate Editor.
TAXRATE_CREATE	Create operations in the Tax Rate Editor.
TAXRATE_DELETE	Delete operations in the Tax Rate Editor.
TAXRATE_VIEW	View operations in the Tax Rate Editor.
UTIL_CACHE_EDIT	Edit a UtilCache instance.
UTIL_CACHE_VIEW	View a UtilCache instance.
UTIL_DEBUG_EDIT	Edit a UtilDebug instance.
UTIL_DEBUG_VIEW	View a UtilDebug instance.
WEBTOOLS_VIEW	Permission to access the WebTools Menu.
WORKEFFORTMGR_CREATE	Create operations in the Work Effort Manager.
WORKEFFORTMGR_DELETE	Delete operations in the Work Effort Manager.
WORKEFFORTMGR_UPDATE	Update operations in the Work Effort Manager.
WORKEFFORTMGR_VIEW	View operations in the Work Effort Manager.
WORKFLOW_MAINT	Use the Workflow Maintenance pages.

**Security Group: FULLADMIN - Full Admin group, has all general permissions.**

ACCOUNTING_ADMIN	ALL operations in the Accounting Manager.
CATALOG_ADMIN	ALL operations in the Catalog Manager.
CATALOG_PRICE_MAINT	Permission required, in addition to other applicable permissions, to maintain product price information including prices, promotions, and price rules.
CONTENTMGR_ADMIN	ALL operations in the Content Manager.
DATAFILE_MAINT	Use the Data File Maintenance pages.
ENTITY_DATA_ADMIN	ALL with the Entity Data Maintenance pages.
ENTITY_MAINT	Use the Entity Maintenance pages.
ENTITY_SYNC_ADMIN	Use the Entity Sync Admin pages.
ENUM_STATUS_MAINT	Use the Enum and Status Maintenance pages.
FACILITY_ADMIN	ALL operations in the Facility Manager.
MANUAL_PAYMENT	Manual Payment Transaction.
MANUFACTURING_ADMIN	ALL operations in the Manufacturing Manager.
MARKETING_ADMIN	ALL operations in the Marketing Manager.
ORDERMGR_ADMIN	ALL operations in the Order Manager.
PARTYMGR_ADMIN	ALL operations in the Party Manager.
PAYPROC_ADMIN	ALL operations in the Payment Processors Setup.
PAY_INFO_ADMIN	ALL Payment Information Operations.
PERIOD_MAINT	Use the Period Maintenance pages.
RULES_MAINT	Use the Rules Maintenance pages.
SECURITY_ADMIN	ALL operations in the Security Management Screens.

SEND_CONTROL_APPLET	Send to the Control Applet.
SERVER_STATS_VIEW	View the Server Statistics pages.
SERVICE_INVOKE_ANY	Permission to invoke any service remotely.
SERVICE_MAINT	Use the Service Maintenance pages.
SHIPRATE_ADMIN	ALL operations in the Shipping Rate Editor.
TAXRATE_ADMIN	ALL operations in the Tax Rate Editor.
UTIL_CACHE_EDIT	Edit a UtilCache instance.
UTIL_CACHE_VIEW	View a UtilCache instance.
UTIL_DEBUG_EDIT	Edit a UtilDebug instance.
UTIL_DEBUG_VIEW	View a UtilDebug instance.
WEBTOOLS_VIEW	Permission to access the WebTools Menu.
WORKEFFORTMGR_ADMIN	ALL operations in the Work Effort Manager.
WORKFLOW_MAINT	Use the Workflow Maintenance pages.

**Security Group: ORDERADMIN - Order Admin group, has all order permissions.**

ORDERMGR_ADMIN	ALL operations in the Order Manager.
----------------	--------------------------------------

**Security Group: ORDERADMIN\_LTD - Limited Order Admin group, has all limited order permissions.**

ORDERMGR_ROLE_CREATE	Limited Create operations in the Order Manager.
ORDERMGR_ROLE_DELETE	Limited Delete operations in the Order Manager.
ORDERMGR_ROLE_UPDATE	Limited Update operations in the Order Manager.
ORDERMGR_ROLE_VIEW	Limited view operations in the Order Manager.

**Security Group: ORDERENTRY - Order Entry Admin group; permissions for creating orders.**

CATALOG_VIEW	View operations in the Catalog Manager.
ORDERMGR_CREATE	Create operations in the Order Manager.
ORDERMGR_NOTE	Create notes in the Order Manager.
ORDERMGR_ROLE_VIEW	Limited view operations in the Order Manager.
ORDERMGR_SALES_ENTRY	Sales Order Entry in the Order Manager.
ORDERMGR_UPDATE	Update operations in the Order Manager.
ORDERMGR_VIEW	View operations in the Order Manager.
PARTYMGR_CREATE	Create operations in the Party Manager.
PARTYMGR_NOTE	Create notes in the Party Manager.
PARTYMGR_UPDATE	Update operations in the Party Manager.
PARTYMGR_VIEW	View operations in the Party Manager.
PAY_INFO_CREATE	Create Payment Information.
PAY_INFO_UPDATE	Update Payment Information.
PAY_INFO_VIEW	View Payment Information.

**Security Group: ORDERPROC - Admin group for restricted order processing.**

ORDERMGR_NOTE	Create notes in the Order Manager.
ORDERMGR_ROLE_VIEW	Limited view operations in the Order Manager.
PARTYMGR_NOTE	Create notes in the Party Manager.
PARTYMGR_VIEW	View operations in the Party Manager.

**Security Group: ORDERSUPPLIER\_LTD - Limited Order Admin group for Supplier Agents.**

ORDERMGR_ROLE_CREATE	Limited Create operations in the Order Manager.
ORDERMGR_ROLE_UPDATE	Limited Update operations in the Order Manager.
ORDERMGR_ROLE_VIEW	Limited view operations in the Order Manager.
ORDERMGR_VIEW	View operations in the Order Manager.

**Security Group: PARTYADMIN - Party Admin group, has all party permissions.**

PARTYMGR_ADMIN	ALL operations in the Party Manager.
----------------	--------------------------------------

**Security Group: VIEWADMIN - Demo Admin group, has all view permissions.**

ACCOUNTING_VIEW	View operations in the Accounting Manager.
CATALOG_VIEW	View operations in the Catalog Manager.
CONTENTMGR_VIEW	View operations in the Content Manager.
ENTITY_DATA_VIEW	View with the Entity Data Maintenance pages.

FACILITY_VIEW	View operations in the Facility Manager.
MANUFACTURING_VIEW	View operations in the Manufacturing Manager.
MARKETING_VIEW	View operations in the Marketing Manager.
ORDERMGR_NOTE	Create notes in the Order Manager.
ORDERMGR_VIEW	View operations in the Order Manager.
PARTYMGR_NOTE	Create notes in the Party Manager.
PARTYMGR_VIEW	View operations in the Party Manager.
PAYPROC_VIEW	View operations in the Payment Processors Setup.
PAY_INFO_VIEW	View Payment Information.
SECURITY_VIEW	View operations in the Security Management Screens.
SERVER_STATS_VIEW	View the Server Statistics pages.
SHIPRATE_VIEW	View operations in the Shipping Rate Editor.
TAXRATE_VIEW	View operations in the Tax Rate Editor.
UTIL_CACHE_VIEW	View a UtilCache instance.
UTIL_DEBUG_VIEW	View a UtilDebug instance.
WEBTOOLS_VIEW	Permission to access the WebTools Menu.
WORKEFFORTMGR_VIEW	View operations in the Work Effort Manager.
WORKFLOW_MAINT	Use the Workflow Maintenance pages.